

Vireio Perception – Short-Cuts/Hot-Keys

Toggles and Menus

Double Tap the right Control key to disable all Vireio shortcut keys

Key	Alternative Key	Function
LCTRL + Q	Double-Click Start button on Xbox 360 Controller	Show/Hide VP Menu To select an item or navigate to a sub-menu, use RETURN or RSHIFT
Double Tap RCTRL		Disable ALL Vireio shortcut keys, Double tap again to re-enable
RSHIFT	RETURN	Select item in VP Menu
ESCAPE		Close VP Menu
LSHIFT + F	LCTRL + F	Show FPS / Frame Time counter
LSHIFT + H	LCTRL + H	Show/Hide HMD Stats
LSHIFT + R	LCTRL + R L+R Shoulder Buttons on Xbox 360 Controller	Reset HMD Orientation / Position
LSHIFT + M		Comfort Mode (can be configured through the VPMENU)
LSHIFT + L		Toggle Depth Perception Mode (ALPHA)
LSHIFT + DELETE		Toggle Oculus VR SDK Pose Prediction (default is on, and recommended it remains like that, only turn off if you are experiencing judder to see if it helps)
LSHIFT + B		Toggle DK2 Black Smear Correction (default is off)
LSHIFT + J	LCTRL + J	Toggle Chromatic Aberration Correction (default is on)
LSHIFT + X		Toggle Free-Pitch / Unlocked Mouse y-axis Mode (when using VRBoost)

LSHIFT + V		Show VRBoost Active Axes and Addresses (for debugging scanner profiles)
Double Click NUMPAD 0		Toggle VR Mouse If VR mouse is active, then double click again will toggle between GUI and HUD scaling mode if within 2 seconds, otherwise it will disable VR mouse
LCTRL + NUMPAD 1		Toggle Floating Menus
MOUSE WHEEL BUTTON	LCTRL + NUMPAD 2 (hot-key for this can also be defined in the VP menu)	Disconnected Screen View
RCTRL + *		Take Stereo Screenshot
LEFT ALT + MOUSE WHEEL BUTTON		<u>CHEAT</u> : Telescopic Sight For games that support a WorldFOV adjustment in VRBoost, this cheat mode will enable a telescopic sight (toggle)
LCTRL + +		Restore current maximum distortion
NUMPAD 5	LCTRL + /	Run the VRBoost Memory Scanner (on compatible games)
NUMPAD 8	LCTRL + ;	Dismiss scanner messages and use Mouse Emulation for head tracking
NUMPAD 4	LCTRL + ,	Move to the Previous candidate scan result (Scan Assist Mode)
NUMPAD 6	LCTRL + .	Move to the next candidate scan result (Scan Assist Mode)

Adjusters

Key	• Mouse	Function
LCTRL	MOUSE WHEEL	Distortion Intensity (Zoom in/out)
LCTRL + TAB	MOUSE WHEEL	Adjust Y offset of Display
LCTRL + LSHIFT	MOUSE WHEEL	Adjust IPD image separation
LCTRL + ALT	MOUSE WHEEL	Adjust World Scale (use with extreme caution)

LCTRL + SPACE	MOUSE WHEEL	Adjust Convergence (use with extreme caution)
---------------	-------------	---

Pressing the backspace on most value adjusters in the VP menu will either return it to its default value or 0